

MIKE Internet License

User Guide



DHI A/S headquarters Agern Allé 5 DK-2970 Hørsholm Denmark

+45 4516 9200 Telephone mike@dhigroup.com www.mikepoweredbydhi.com

Company Registration No.: DK36466871



PLEASE NOTE

COPYRIGHT	This document refers to proprietary computer software, which is protected by copyright. All rights are reserved. Copying or other reproduction of this manual or the related programs is prohibited without prior written consent of DHI A/S (hereinafter referred to as "DHI"). For details please refer to your 'DHI Software Licence Agreement'.
LIMITED LIABILITY	The liability of DHI is limited as specified in your DHI Software License Agreement:
	In no event shall DHI or its representatives (agents and suppliers) be liable for any damages whatsoever including, without limitation, special, indirect, incidental or consequential damages or damages for loss of business profits or savings, business interruption, loss of business information or other pecuniary loss arising in connection with the Agreement, e.g. out of Licensee's use of or the inability to use the Software, even if DHI has been advised of the possibility of such damages.
	This limitation shall apply to claims of personal injury to the extent permitted by law. Some jurisdictions do not allow the exclusion or limitation of liability for consequential, special, indirect, incidental damages and, accordingly, some portions of these limitations may not apply.
	Notwithstanding the above, DHI's total liability (whether in contract, tort, including negligence, or otherwise) under or in connection with the Agreement shall in aggregate during the term not exceed the lesser of EUR 10.000 or the fees paid by Licensee under the Agreement during the 12 months' period previous to the event giving rise to a claim.
	Licensee acknowledge that the liability limitations and exclusions set out in the Agreement reflect the allocation of risk negotiated and agreed by the parties and that DHI would not enter into the Agreement without these limitations and exclusions on its liability. These limitations and exclusions will apply notwithstanding any failure of essential purpose of any limited remedy.



CONTENTS

MIKE Internet License User Guide

1	General information	1
2	Default settings	2
3	Getting started	3
4	Offline mode	4
5	Web portal	
5.1	Internet license servers' status	
5.2	Portal Features	
5.3	History	
5.4	Active Users	
5.5	Licenses	
5.6	Forgot password / Changing passwords	
6	Troubleshooting connection problems	
6.1	Error messages	
6.2	SSL Certificate	
6.3	Proxy Server	



1 General information

The MIKE Internet License service is for customers who have opted for using an Internet license instead of a dongle license. For you to gain access to the Internet license server, DHI will create One administrator license account when we have received your order. The administrator will then be able to create all other user accounts including other administrators. Therefore, please contact your local internal administrator if you need access to your company's DHI Internet License.

NB. The login for the Internet license service is for license access in MIKE software only and cannot be used for the mikepoweredbydhi.com download page etc.

The Internet license can be used for all MIKE software from version 2016 onwards.



2 Default settings

These settings are pre-set in all MIKE software products and do not need any changes. However, should you need to restore the default settings, please use the information below:

From MIKE 2019 and onward, these Internet license servers are used:

- https://dk.license.mikebydhi.com/svc
- https://license2.mikebydhi.com/svc

with HTTPS (port 443).

To be able to connect to the Internet license, it is required that service port 443 is open for an SSL connection.

Be sure that no firewalls are blocking the port. Contact your company's IT department for assistance. When contacting your company's IT department, then remember also to ask them if your company uses proxy servers or SSL inspection software. This information can be helpful when setting up the internet License.



3 Getting started

Once you have received your credentials for the Internet License service, you are ready to connect. Opening the DHI License Management Utility on your PC by right click then choose 'run as admin'.

It is not necessary to install the DHI License Manager separately to use the Internet License.

~~~~				VV	IVER	$\rightarrow$	<b>3</b> 45	KDK		- AKT	$\checkmark$	-
	In	ternet	Lice	nse S	Serve	r	A					
License Server	Server 9 Serving											
Internet License Server		🌱 Offline										
MIKE URBAN+ 2019	Internet license server											
MIKE Animator Plus 2020	User name (email):	xxx@dhigroup.com									$\sim$	Connect
MIKE URBAN 2020 Remote Simulation 2020	Password:	••••										Settings
Remote Simulation 2020 Remote Simulation Server 2020	-dasword.											occuriga
MIKE + 2021	Available licenses											
LITPACK 2022	Program	Version	Variant	Order Id	Alias	Model s	Cores	Seats	Free seats	Product Id	Valid From	Valid To ^
MIKE 11 2022			variarit									
MIKE 21 2022	MIKE 1DECOLAB	2022		723	DHI default3	unlimited	unlimited	unlimited unlimited	unlimited	MIKE+ MIKE+	2020-09-18 2020-09-18	unlimite
MIKE 21C 2022	MU_CS_Bio_Process m11ecolab	2022		723 723	DHI default3 DHI default3	unlimited unlimited	unlimited unlimited	unlimited	unlimited unlimited	MIKE+	2020-09-18	unlimite:
MIKE 3 2022	m11ecolab mflood m21ecolab	2022		723	DHI default3 DHI default3	unimited	unlimited	unlimited	unimited	MIKE+	2020-09-18	unimiter
MIKE Animator Plus 2022	mflood_m21ecolab	2022		723	DHI default3 DHI default3	unlimited	unlimited	unlimited	unlimited	MIKE+	2020-09-18	unimiter
MIKE FLOOD 2022	mflood_m21necolab mflood_m21fmel	2022		723	DHI default3 DHI default3	unimited	unlimited	unlimited	unlimited	MIKE+	2020-09-18	unimiter
MIKE HYDRO 2022 MIKE SHE 2022	millood_m21mer	2022		723	DHI default3	unlimited	unlimited	unlimited	unlimited	MARINE PP	2020-09-18	2023-0:
Remote Simulation 2022	BathEdit	2022		723	DHI default3	unlimited	unlimited	unlimited	unlimited	MARINE PP	2015-09-24	2023-0:
Remote Simulation Server 2022	GridEdit	2022		723	DHI default3	unlimited	unlimited	unlimited	unlimited	MARINE PP	2015-09-24	2023-01
WGEO	PlotComposer	2022		723	DHI default3	unlimited	unlimited	unlimited	unlimited	MARINE PP	2015-09-24	2023-01
FEFLOW	ProfileEdit	2022		723	DHI default3	unlimited	unlimited	unlimited	unlimited	MARINE PP	2015-09-24	2023-01
FEFLOW Batch	Result Viewer	2022		723	DHI default3	unlimited	unlimited	unlimited	unlimited	MARINE_PP	2015-09-24	2023-01
All network licenses	TSEdit	2022		723	DHI default3	unlimited	unlimited	unlimited	unlimited	MARINE PP	2015-09-24	2023-0:
All Internet Licenses	WS Basic	2022		723	DHI default3	unlimited	unlimited	unlimited	unlimited	MARINE PP	2015-09-24	2023-0:
C Local settings	Animator	2022		723	DHI default3	unlimited	unlimited	unlimited	unlimited	MARINE_PP	2015-09-24	unlimiter 🗎
	<											>
	Refresh											P
	Refresh											بر
	2 - 2 - 2											

Enter your credentials before clicking Connect. Make sure you do not include any blanks/spaces around neither username nor password.

When connected you will be able to see the available licenses as shown above.

Clicking the Sessions tab at the top, will show you a list of who is currently using the licenses.



# 4 Offline mode

Offline mode allows you to check out licenses from the internet license server to be used locally and thereby give you the flexibility to work offline.

Offline mode is available for MIKE software from version 2020 and onwards. To check out licenses it is required to have a PROFESSIONAL license and to be online while checking out the licenses.

Firstly, open the DHI License Management utility and connect to the internet license server using your username and password, as described in the previous section. Then, select Offline in the tab menu as shown below.

わ DHI License Management									-		×
	Inte	ernet l	icense	Serve			<u>XI</u> ×				7
License Server Internet License Server MIKE URBAN+ 2019 MIKE URBAN+ 2019 MIKE URBAN+ 2020 MIKE URBAN-2020 MIKE+ 2021 MIKE+ 2021 MIKE+ 2021 MIKE+ 2022 MIKE 11 2022 MIKE 21 2022 MIKE 21 2022 MIKE 22 2022 MIKE 22 2022 MIKE 22 2022 MIKE 54 Animator Plus 2022 MIKE SHE 2022 MIKE 2022		Y Offine     xxxx @chigroup     MIKE 11 2022     222	√ Variant:		Alas	Model size	Cores	Seats	Free seats	Checkout Valid Fro	
G - S FEFLOW Bath     All network licenses     All network licenses     Local settings	¢						OK	Apply	Close	>	q

Under Product, select the product package you would like to check out. It is possible to check out more than one product package, but they must be checked out one after another. Only one seat can be checked out at a time and all modules under the product package will be checked out. When a product package is selected a list of available Order ID's will be shown under Oder ID. Select the Order ID you would like to use.

Finally, Select the check out expire date from the calendar. The offline license can be checked out for a period of up to 14 days. When expire date is reached, check out license will be returned back to the internet license poll. Please note, that it is not possible to return offline licenses manually.

Click 'Checkout'. A popup window will appear asking you to confirm the check out. Click 'OK'. The check out process will take few seconds until a list of offline licenses showing up. Then the check out process is completed successfully and the offline licenses are activated.



			icense				D			
	Inte	rnet L	icense	e Serv	er					
License Server	Server 🙎 Sessions	🖌 Offline								
MIKE URBAN+ 2019 MIKE Animator Plus 2020	Internet License Server									
MIKE URBAN 2020	User name (email):	xxx@dhigroup.	com							Checkout
Remote Simulation 2020	Product:	MIKE 11 2022	<ul> <li>Variant</li> </ul>	: ~						
Remote Simulation Server 2020 MIKE + 2021	Order Id.:	723 🗸								
LITPACK 2022	Check out date: 2	021-10-04								
MIKE 11 2022	Check out expire date:	021-10-04 🔲	•							
MIKE 21 2022		021-10-04 @								
MIKE 21C 2022 MIKE 3 2022	Offline licenses									
MIKE S 2022 MIKE Animator Plus 2022	Program	Version	Variant	Order Id	Alias	Model size	Cores	Seats	Free seats	Valid ^
MIKE FLOOD 2022	M11RESERVOIR	2022		723	DHI default3	unlimited	unlimited	1	1	2021
MIKE HYDRO 2022	M11ICE	2022		723	DHI default3	unlimited	unlimited	1	1	2021
MIKE SHE 2022	M11_DRiFt	2022		723	DHI default3	unlimited	unlimited	1	1	2021
Remote Simulation 2022	M1FEH	2022		723	DHI default3	unlimited	unlimited	1	1	2021
Remote Simulation Server 2022	M11FF	2022		723	DHI default3	unlimited	unlimited	1	1	2021
🗓 WGEO	M11DA	2022		723	DHI default3	unlimited	unlimited	1	1	2021
FEFLOW	M11GIS	2022		723	DHI default3	unlimited	unlimited	1	1	2021
FEFLOW Batch	MIKEHYDRO_LOAD	2022		723	DHI default3	unlimited	unlimited	1	1	2021
All network licenses	MIKEHYDRO_TemporalA	n 2022		723	DHI default3	unlimited	unlimited	1	1	2021
All Internet Licenses	M11QUASIWQ	2022		723	DHI default3	unlimited	unlimited	1	1	2021
C Local settings	M11ST	2022		723	DHI default3	unlimited	unlimited	1	1	2021
		2022			port for the	Read and	16 (A) (A)			~~ ×
	<									,

Your application may use multiple license modules which are included in different product packages. Therefore, it is recommended to test the offline licenses in advance. The test can be performed like this, tum off the internet connection and test the application you would like to use offline. If any error message appears saying a missing license or model runs in Demo mode, turn on the internet connection and check out the additional licenses needed.

When offline, a list of offline licenses will show including Order ID and Valid To date. The offline licenses for a product package will also be displayed under 'Available Licenses' when selecting the product package or Internet License Server on the main menu.



# 5 Web portal

You find the web portal here: https://license.mikepoweredbydhi.com.

In the web portal you have access to various levels of information about your company's license and users depending on your rights.

To log into the portal please use the same credentials as for connecting to the license.

INTERNET LICENSE	MIKE	CONTACT LOGIN STATUS
	Login	
	Email xxxt@dhigroup.com	
	Passward	
	LOGIN	
	Forgot Password?	

# 5.1 Internet license servers' status

You can check the operational status of the Internet license servers by checking the Status page https://license.mikepoweredbydhi.com/internetlicense/Status.



You can also find the link to the status overview by starting MIKE Zero.

The operational status of the different Internet license servers and of the web portal are listed there. Planned maintenance of the servers will also be announced on the web portal.



INTERNET LICENSE	MIKÊ	CONTACT LOGIN	STATUS
All Systems operational.			
Systems			
Internet License Service			operational
Internet License Service (Failover)			operational
Web Portal			operational
Incidents			
8/17/2018 221:47 PM Planned maintenance of the servers Servers will be updated on Tuesday, August 21 at 9:55 pm. UT <i>Update 82.22.018 22.62.5 AM</i> Servers updated.	Internet License Ser TC/GMT. Internet license service and web portal will not be available during the update (3-10 minut		Web Portal resolved
Contact us Login Status	©DHI Group	Disclaimer Terms of use Privacy	

# 5.2 Portal Features

There are several portal features and they are explained in more details in the following sections. Some of the features are only available to an administrator.

### 5.2.1 Dashboard

You will be directed to the dashboard when you log on to the portal. The dashboard gives you a quick overview of the usage of MIKE products in the shared pool of licenses within your organisation.

ft Home	Dashboard	🚨 Use	ers 🗏 History	(+) Active Users	≫ Licenses 🗹 Sta	tus		
0			All products	~	All business units	~	Today	•
Licenses nearing exp	iry In 3 months		3		5		0d 0h 0m 10s	
Seats in use now			9 Peak seats in use		Seats shortage events		Usage duration on average	
View licenses		>			Seats Usage Hist	ory Data		
1			1.5					
Current active users		_	2.5				(	
View active users		•	2					-
			1.5				/	
			0.5				/	
			0 0 17. Sep 01:00	02:00 03:00	04:00 05:00 Tim	06:00 07:00 re	08:00 09:00 10	00 11:00



You can get an idea of licenses expiring within the next 3 months and an estimate of the number of seats in use over a period of time. The number of seats in use is calculated by adding up all modules in use, including the engine and editors. Therefore, this number may exceed the number of editor seats that you have purchased.

The Current active users counter shows the number of all users who are currently using MIKE licenses. Clicking the View active users will show you who they are.

NB: The numbers only update when entering the Dashboard



# All products 110 Peak seats in use

The information above the graph and the graph itself can be filtered based on products, business units and datetime.

Clicking on **All products** will allow you to filter the different MIKE products which you have in your license.

**Peak seats in use** are calculated in the same way as number of seats in use but only displays the maximum number of seats based on the product chosen, business unit* and datetime. Please be aware that the number of seats is calculated by adding all product modules in use including the engine and editor seats. Therefore, the total number may exceed the number of editor seats you have purchased.

*The business unit information will be available for future events after it has been set up



Clicking on **All business units** will allow you to filter based on business units. Please be aware that this feature is only available if you have filled in the business unit fields for each user in the system. This is done through the Edit details option for each user.

**Seats shortage events** is a counter that tracks the number of times the license system is being asked for a license where it is not available. The reasons for unavailability may be several:

- There may be too many users with access to the license
- You may have too few licenses for your workload
- You may have tried to use a module that you do not own
- You have tried to use a module that has expired
- You may have tried to use a module in a version that you do not own.

Feel free to contact mike@dhigroup.com if you need further information about the shortage.



Clicking on **Today** will allow you to change the date range applied.

**Usage duration on average** is the average time a seat is being used based on the product chosen, business unit and datetime.

NB: The date and time is localised to your local region based on your browser settings.

## 5.2.2 Users

The Users tab shows you all the users registered within your company who have access to use the Internet license. As a standard user you will only be able to edit your own account. An administrator will have several additional options for managing the account and users.



INTERNET LI	CENSE			MIKE	xxx.@dhigr	LOGOUT			
A Home	Dashboard	L Users	i≣ History	(•) Active Users	Licenses	🗹 Status			
+ Add User								Search	9
Jser ID	†↓ Name		Country	↑↓ Office ↑↓ E	Business Unit	t Expiry	1 Order ID	1. Actions	
@qq.com	Yingying								Modify •
@dhigroup.com	Amit		India			01-01-2050			Modify -
									Modify -
@dhigroup.com	Alex	faman							Modify 🕶
@dhigroup.com	Aditya	al l	India			01-01-2050			Modify -
@dhlgroup.com	Alejandro	ue Te	Argentina						Modify 👻
@dhigroup.com	Amit								Modify <del>*</del>
@dhigroup.com	Antonio	miari							Modify *
@dhigroup.com	Adriaan	droek				01-01-2050			Modify -
@dhigroup.com	Arnold	mann	United States			01-01-2050			Modify <del>-</del>
				Showing 1 to 10 of 215 ro	ws 10 • rows per p	page First Previous	1 2 3 4 5	22 Next	t Last go to
	Contact us Status			©DHI Group		Disclaimer	Terms of use Privacy		

## User options

- View all users in the organisation
- Edit your own user details
- Change your own password
- Subscribe / unsubscribe on notifications

### Administrator options

NB: Administrators have an admin icon besides the modify button.

By using the Add User and Modify buttons an Administrator may.

Modify -	• Add new users and delete existing users. NB: a deleted user cannot be restored.
Disable user	<ul> <li>Dis- and enable users. A disabled user will not be able to access and use the Internet license</li> </ul>
Remove admin	Give and remove admin rights to/from users. You can have multiple
Make admin	administrators within an organisation
Edit details	Edit details for all users, incl. Business Unit
Change password	
Delete user	

0

# 5.3 History

The History tab is available to all users and shows the historical usage for all users in your organisation. You can search and filter on users, product modules (modules as displayed), products and so on for all fields shown below.

NB: the datetime displayed on the web portal is localised to your region based on your browser settings.



INTERNET LICI	ENSE		MI	XXX@dhigroup.cor			
A Home	Dashboard	<b>≜</b> Users i≣ F	History	(··) Active Users	Licenses	🗹 Status	
🛓 Download details						Today 🗸 Search	) •
ame î	🕽 Business Unit 🌐 O	ffice 1 Module	1 Product	1 Order ID 1 A	lias 🕕 Hostname	Start Time [+02:00]	↑↓ Duration ↑↓
fam Leonard William		MZAPPSHELL	MARINE_PP	723	vNC26801744-21	8/10/2021, 6:46:23 PM	00d 16h 25m 11s
fen Leonard William		MZAPPSHELL	MARINE_PP	723	vNC11825756-98	8/11/2021, 11:04:40 PM	00d 00h 23m 15s
fam Leonard William		MZAPPSHELL	MARINE_PP	723	vNC26801744-21	8/10/2021, 6:30:12 PM	00d 16h 41m 28s
fam Leonard William		MZAPPSHELL	MARINE_PP	723	vNC26801744-21	8/10/2021, 6:42:37 PM	00d 16h 28m 58s
Intra-Leonard William		MZAPPSHELL	Other	90723	UKPC004	8/11/2021, 3:15:02 PM	00d 00h 00m 33s
la Reyhard Manualah		MU_CS_ModelManager	MIKE+	723		8/11/2021, 5:30:18 PM	00d 04h 32m 41s
ta Rayhani Massulah		MU_CS_ModelManager	MIKE+	723	AIRM-PC4	8/11/2021, 9:49:32 AM	00d 01h 48m 52s
la Reylant Manualah		MU_CS_ModelManager	MIKE+	723		8/11/2021, 11:38:57 AM	00d 05h 51m 15s
la Reyford Manualah		MU_CS_ModelManager	MIKE+	723		8/10/2021, 3:12:52 PM	00d 18h 35m 47s
Centro Lavarila		MZAPPSHELL	MARINE PP	723	ael-pc1	8/11/2021, 9:36:33 PM	00d 02h 36m 31s

You can change the time range of the historical data by clicking on **Today** and selecting from the options within the menu.

You can also download the details by clicking the download button. The downloaded data is based on the criteria you have chosen.

NB: Downloaded data have the datetime set as GMT instead of local time.

## 5.4 Active Users

The Active Users tab (available to all users) shows all currently active users in your organisation. You can search and filter for users, product modules (modules as displayed), hostname, etc. for all fields shown below.

INTERNET LI	CENSE		MI	KE	xxx@dhig	LOGOUT		
A Home	Dashboard	🚨 Users	≣History	(1) Active Users	Licenses	🗹 Status		
							Search	63
lame	Business Unit ↑↓	Office Module	Product ↑↓	Order ID A	lias Hostname	Active Since [+02:00]	<b>Duration</b>	Release ↑↓ Seat
dati Laurard William		MZAPPSHELL	Other	77230	UKPC006	9/30/2021, 10:10:21 PM	00d 13h 46m 14s	×
ills Rephart Manualah		MU_CS_Basic	MIKE+	77230		9/30/2021, 3:05:50 PM	00d 20h 50m 45s	×
its Reptart Manufalt		MU_CS_PipeFlow	MIKE+	77230		9/30/2021, 3:42:57 PM	00d 20h 13m 38s	×
de Rechard Manual M		MU_ModelManager	MIKE+	77230		9/30/2021, 10:46:02 PM	00d 13h 10m 33s	×
its Reyford Manualati		MU_ModelManager	MIKE+	77230		9/30/2021, 3:16:55 PM	00d 20h 39m 40s	×
the Replace's Managalatic		MU_CS_Basic	MIKE+	77230		9/30/2021, 3:16:55 PM	00d 20h 39m 40s	×
da Rephani Massulah		MU_ModelManager	MIKE+	77230		9/30/2021, 3:05:49 PM	00d 20h 50m 46s	×
ils Reyford Manualsh		MU_CS_Rainfall_Run	off MIKE_URBAN	723		9/30/2021, 9:02:34 PM	00d 14h 54m 01s	×
da Rayhari Massulah		MU_CS_Basic	MIKE+	77230		9/30/2021, 10:46:03 PM	00d 13h 10m 33s	×
		MU_WD_Basic	MIKE+	77230	AKYO-PC1	10/1/2021, 11:23:03 AM	00d 00h 33m 32s	×

## Releasing license seats

If you have Administrator rights, you have access to this feature.



If a computer or a model crashes, the taken modules will normally be released automatically after approximately 15 minutes making them available for use. However, this will not be shown in the available seats overview. It may take up to 2 hours before it shows in the portal.

If there is a need to release license seats, an administrator can click the  $\mathbf{x}$  for a specific active user and release the license seat. This seat will be available immediately.

NB: There is a small risk that the released license seat is immediately taken by another user within your organisation if the user starts the software just as the seat is released.

## 5.5 Licenses

In the licenses tab, you get an overview of all the licenses that are available to you in your organisation. The licenses are organised into products. You can search and filter for product modules (modules as displayed), expiry date, and so on for all fields shown below.

NB: It is important to note the difference between the **Product** and the **Order ID** fields. The Order ID is the License Registration number and may contain many products. Most organisations have only one Order ID.

INTERNET LICENSE				MIKE Powerda DM	MIKE				
A	t Home	Dashboard	Lusers	i≣ History (o	) Active Users	Licenses 🗹 Status			
							Search	0	
	Product	†↓ Moo	lules Order ID	1 Alias 1 Expiry Date	e î↓ Seats Seats	In Use Assigned Users	Actions		
	MIKE_21C(2022)	13	723	15-01-2023		3		Modify <del>-</del>	
	MIKE_21C(2022)	2	723	01-01-2050		3		Modify -	
	MIKE_3(2022)	4	723	01-01-2050		3		Modify <del>~</del>	
	MIKE_3(2022)	47	723	15-01-2023		3		Modify -	
	MIKE_ANIMATOR(202	2) 1	723	15-01-2023		3		Modify <del>-</del>	
	MIKE_BASIN(2022)	23	723	15-01-2023		3		Modify <del>~</del>	
	MIKE_CMAP(2022)	1	723	15-01-2023		3		Modify ~	
	MIKE_FLOOD(2022)	10	723	01-01-2050		3		Modify <del>~</del>	
	MIKE_FLOOD(2022)	23	723	15-01-2023		3		Modify <del>~</del>	
	MIKE_OPERATIONS(2)	022) 23	723	15-01-2023		3		Modify <del>~</del>	

The fields **Seats** and **Seats in Use** will only display information when the + button to the left of the product name is clicked.

#### See the following example.

+	MIKE_21C(2022)	2	723	01-01-2050			2	Modify -
-	MIKE_3(2022)	4	723	01-01-2050			2	Modify -
		m3fmGPU MIKE_CMAP MIKE_CMAP WS_Analysis			unlimited unlimited unlimited unlimited	3 0 0	@dhigroup.com @dhigroup.com	
+	MIKE_3(2022)	47	723	15-01-2023			2	Modify 🕶
+	MIKE_ANIMATOR(2022)	1	723	15-01-2023			2	Modify <del>*</del>
+	MIKE_BASIN(2022)	23	723	15-01-2023			2	Modify <del>-</del>
+	MIKE_CMAP(2022)	1	723	15-01-2023			2	Modify -



The **Seats** field will show the number of available seats while the **Seats in Use** will display the number of seats currently in use.

#### Modify

The "Modify" action gives access to this functionality for the license administrator:

- Define / edit an alias for the Order ID.
- The functions that previously was labelled "Add assigned users".

#### **Edit Alias**

This function gives to the license administrator the option to give a nickname / alias for the order IDs for the licenses. This functionality is particular useful if available licenses have different order IDs.

The dialogue for specifying the alias looks like this.

Change Alias			×
Order ID	723		
Alias			
		Confirm	Cancel
723	15-01-2023	_	2

When the alias is confirmed, then then list of licenses is updated accordingly.

#### Add assigned users

Adding assigned users is an advanced feature that allows the license administrator to assign a specific **Order ID** (license number) to selected users.

By default, all enabled users have access to all **Products** and all **Order IDs** in your organisation. To restrict access for a user to a specific **Order ID**, an administrator can assign a user or a group of users to a selected **Order ID** by clicking the **Add assigned user(s)** button as shown below.

A user can only be assigned to **ONE** Order ID at any one time. Once a user is assigned to an **Order ID**, that user can only access products and product modules associated with that **Order ID**.



	INTERNET LICI	ENSE		MIKE			XXX@dhigroup.com 📄 LOG OUT		
	A Home	Dashboard	L Users	≣ History	(•) Active Users	Licenses	🗹 Status		
	Product	↑. Module:	s Order ID	Alias Expiry Dat	e 🔃 Seats	Seats In Use	Assigned Users	Search 2	
+	MIKE_21C(2022)	13	723	15-01-202			2	Modify ~	
+	MIKE_21C(2022)	2	723	01-01-2050	)		2	Modify -	
+	MIKE_3(2022)	4	723	01-01-2050	)		2	Modify ~	
ŧ.	MIKE_3(2022)	47	723	15-01-2023	3		2	Modify -	
+	MIKE_ANIMATOR	1 (2022)	723	15-01-2023	3		2	Modify -	
+	MIKE_BASIN(202	2) 23	723	15-01-2023	1		2	Edit alias	
ŧ.	MIKE_CMAP(2022	2) 1	723	15-01-2023	3		2	Assign multiple users	
+	MIKE_FLOOD(202	22) 10	723	01-01-2050	)		2	@dhigroup.com @dhigroup.com	
ŧ.	MIKE_FLOOD(202	22) 23	723	15-01-202	3		2	@dhigroup.com	
ŧ.	MIKE_OPERATIO	NS(2022) 22	723	15-01-2023	1		2	@dhigroup.com	

An additional dialog menu will be shown if the Assign multiple users option is clicked:

Multi Assign User		×
Target Order ID : 723		
Unassigned user(s)	Assigned user(s)	
Search	Search	
@qq.com	undo	*
@dhigroup.com @dhigroup.com	**	
dhigroup.com @dhigroup.com	>	
@dhigroup.com a@dhigroup.com	<	
@dhigroup.com	**	
@dhigroup.com @dhigroup.com	redo	
@dhigroup.com @dhigroup.com		
@dhigroup.com		
@dhigroup.com		-

## Remove assigned users

An administrator can remove assigned users by clicking the  $\mathbf{x}$  button next to the user's email address in the expanded view of a product.

-	MIKE_3(2022)	47	723	15-01-2023			2	Modify 👻	
		M21Overland			unlimited	0	@dhigroup.com 🗙		
		m321nos			unlimited	0			
		m321nos			unlimited	0			
		m321npa			unlimited	0			
		m321nsa			unlimited	0			
		m321nsa			unlimited	0			

Alternatively, an administrator can remove assigned users by clicking the **Assign Multiple Users** option under **Add assigned user(s)** and remove the assigned user.



Multi Assign User		×
Target Order ID : 723 Unassigned user(s)	Assigned user(s)	
Search	Search	
@qq.com	undo @dhigroup.com	-
@dhigroup.com @dhigroup.com	••	
@dhigroup.com		
@dhigroup.com	>	
@dhigroup.com	<	
@dhigroup.com		
@dhigroup.com	44	
@dhigroup.com	redo	
@dhigroup.com	Tedo	
@dhigroup.com		
@dhigroup.com :@dhigroup.com		
@dhigroup.com		
adhigroup.com ▼		-
Apply Changes Res	set	

# 5.6 Forgot password / Changing passwords

If a user has forgotten the password or wants to change the password for the personal account, then this operation can be performed in these ways:

- Use the "Forgot password?" at the login page to the DHI Internet License Portal. Then the password for the specified account/e-mail address is set to an auto generated password, which is sent to the e-mail account.
- Get the local administrator for the MIKE products to change the password for the user.
- The user log on the DHI Internet License Portal and finds the account under the "users" tab, then use the change password option under actions. This option only works if the user can remember the current password.


Be aware that MIKE programs only read the configuration when starting, so changing the password for an user with running MIKE programs will make these programs fail, and only recovery for this is changing password back to the original value. It is recommended to let any running MIKE job for a user account finish before changing the password for the account.



# 6 Troubleshooting connection problems

## 6.1 Error messages


## 6.1.1 Error message 1



This error message indicates a network connection or configuration error. The PC is not able to resolve which address is behind "dk.license.mikebydhi.com".

Please check if you can login to http://dk.license.mikebydhi.com/licleaseweb/home.


#### 6.1.2 Error message 2



This error message usually means that something is blocking the PC from connecting to the internet license server. It may be a firewall or some other network rules.

Some users have to use a "proxy" to access the Internet resources (it can work transparently for them when they use IE, but it has to be setup manually for the Internet license).

#### 6.1.3 Error message 3



Please check that username and password are correct and that you have a valid license and account. Make sure that the latest service packs are installed for your MIKE products.



## 6.1.4 Error message 4

DHI License Management	×
No license for MIKE FLOOD 2020 to checkout in offline mode	
ОК	

This error message means that you are trying to check out licenses for a product while the Internet license server is not connected. Make sure to be connected to the internet and that credentials for the Internet license server are not correct. Reconnect/refresh internet license server before trying again to check out internet licenses.

#### 6.1.5 Other Error messages

If you get other error messages than these, please contact mike@dhigroup.com about your problems. Please include screen dumps of error messages and these logfiles:

- C:\Users\<user_login>\AppData\Roaming\DHI\LicSys\NetLmLcw.log
- C:\ProgramData\DHI\LicSys\Relay\netImrelay.log
- C:\Windows\System32\config\systemprofile\AppData\Roaming\DHI\LicSys\NetLmLcw.log (if running on remote simulation)

You may also want to look at our FAQ: https://faq.dhigroup.com/

# 6.2 SSL Certificate

Make sure that you have the latest Windows updates and the latest service packs for your MIKE 2022 products. The software comes with information that is used for validating the certificates in Internet License solution.

Current certificates in DHI Internet License solution:

- SSL certificate for dk.license.mikebydhi.com is valid to May 30, 2022. It is issued by GlobalSign Root CA.
- SSL certificate for license2.mikebydhi.com is valid to September 8, 2022. It is issued by Sectigo RSA Domain Validation Secure Server CA.
- Certificate for license.mikepoweredbydhi.com is valid to February 7, 2022. It is issued by GlobalSign GCC R3 DV TLS CA 2020.

The first two certificates are for the DHI Internet License Service, and the third one is for the DHI Internet License Portal. The above information reflects status on 1st October 2021, and DHI will renew the certificates, when they are nearing the expire date, or replace the certificates, if they are revoked or there are doubt about their status.

DHI software using the DHI Internet License service makes a strong check on the SSL certificates from the DHI Internet License Servers. The software checks that the pinned public key in the certificate installed on the Internet License Servers matches certificates issued for DHI Internet License Service. If the certificate check fails, then DHI applications will not communicate with DHI Internet License Service, and applications can only run in demo mode.

The certificate check used also means that if any network security program checks communication between DHI programs and DHI Internet License Service and in this process replaces or manipulates the certificates DHI Internet License will not work. Exceptions for DHI Internet License should be configured in these internet security products.



# 6.3 Proxy Server

From version 2017 onwards, it is possible to use these proxy servers: HTTP, SOCKS4, SOCKS4a, SOCKS5 and SOCKS5a, also with authentication if it is required. Only the HTTP proxy type was tested with MIKE 2019. The Proxy server address must be entered as shown below (square brackets [..] denote optional parameters. The default port value is 1080:

- proxyserver[:port] HTTP proxy, it is the same as the next one (http://...)
- http://[user:password@]proxyserver[:port]/ HTTP proxy server
- socks4://[user:password@]proxyserver[:port]/ SOCKS4 proxy server
- socks4a://[user:password@]proxyserver[:port]/ SOCKS4a proxy server
- socks5://[user:password@]proxyserver[:port]/ SOCKS5 proxy server
- socks5h://[user:password@]proxyserver[:port]/ SOCKS5a proxy server

Or you can use Proxifier (or similar) to connect.

Communication with the license server can be tested from the DHI License Management utility, by pressing the **Connect** button. The Proxy settings can also be changed in the Internet License Server Settings window opened with the **Settings...** button.